## SET CAMERA BUTTON TO WORK WITH SIMON

This should make the tablet's camera button work with SIMON. If you want the camera to work outside of SIMON, you have to put these settings back to their defaults.

1. On the Desktop, Double Click on the Motion Dashboard



2. On that Window, click on the Pen & Tablet button on the left side of the window

Motion Dashboard	_ = <b>X</b>
Display	Motion
Display	Rotate Screen Display Settings
Pen & Tablet	
Power	Dim   Bright
🔒 Security	Display Scheme:
	To extend battery life, dim display after. idle 30 min 💌

3. Click on the Tablet PC Settings button

Motion Dashboard			_ = x	
Pen & Tabl	et		Motion	
Display	Pen:	Pen & Input Devices		
Audio				
Pen & Tablet	Tablet:	Tablet PC Settings		
💮 Wireless	Digitizer:	Calibrate Digitizer		
Power				
Security	Fingerprint Reader:	Navigation Settings		
	Other Devices		1	
	Enabl	le RFID Reader		
	Enabl	le Bar Code Scanner		
			<b>W</b>	

4. Click on the Buttons tab in the top, left corner of the window



5. Scroll down in the window until 'Camera Button' is displayed in the Tablet Button column

Tablet PC Settings		l	x
Display Buttons O	ther		
Button <u>s</u> ettings for	Primar	y landscape	•
Button location:	Detaile	d view:	
To change an action	n associated with a t	-•• tablet button, tap th	e
Tablet button	Press	Press and hold	·
Enter Button	Enter	(Repeat)	
Camera Button	F10	Show or hide	
Barcode Button	Start C:\Windo	Show or hide	
RFID Button	Start C:\Windo	Show or hide	-
	<u>C</u> hange	<u>R</u> eset	
		Consul a	

6. Click the 'Change' button

Tablet PC Settings	
Display Buttons Other	
Button <u>s</u> ettings for: Primary landscape	
Button location: Detailed view:	
To change an action associated with a tablet button, tap the button name and then tap Change.	
Tablet button Press Press and hold	
Enter Button Enter (Repeat)	
Camera Button F10 Show or hide	
Barcode Button Start C:\Windo Show or hide	
RFID Button Start C:\Windo Show or hide 👻	
<u>C</u> hange	
OK Cancel Apply	

7. In the top field, click the Down Arrow and choose "Press a key or key combination"

Tablet PC Settings		
Display Buttons Other		
Button settings for: Primary la	andscape	
Button location: Detailed	Tablet Button Actions	
	Select actions for the Camera Button button	
	Descrite a closes of the camera bactori bactori.	
	Settinas	
To change an action associated with a tab button name and then tap Change.	Press the key or key combination you want to use when you press this tablet button.	
Tablet button Press F	Kevs: F10	
Enter Button Enter (		
Camera Button F10 S	Clear	
Barcode Button Start C:\Windo S		
RFID Button Start C:\Windo S	The action is repeated when you press and hold the button. Or, you can select a different action below.	
	Press and hold: Show or hide Windows Mobility Center 🔻	
OK Ca	Settings	
	You do not need to change the settings for this action.	
	What is press and hold?	
	OK Cancel	

8. In the Keys field, click in the field to bring up the tablet keyboard



9. Click the "Fn" button in the lower right of the keyboard and then click the "F10" button on the top row of the tablet keyboard (if you do this while docked and using a mouse and external keyboard just press "F10"). The end result of your action should look like this.

Tablet Button	Actions	22
Select actions f	or the Camera Button button.	
Press:	Press a key or key combination	•
Settings		
Press the key or press this tablet	key combination you want to use when you button.	
Keys:	F10	
	Clear	
The action is repe you can select a o Press and <u>h</u> old:	ated when you press and hold the button. C lifferent action below.	)r, ▼
You do not need	to change the settings for this action.	
What is press and	hold? OK Cancel	

10. Click OK and OK to get back to the Motion Dashboard screen.

Select action	s for the Califera button t	baccon.	
Press:	Press a key or key com	bination 🔻	
Settings			
Press the key	or key combination you want	t to use when you	
press this tal	let button.		To wood builton for use of some
			To reset button for use of came
Keys:	F10		
			Outside of SIMON - click here
	(	Clear	
		Clear	
		Clear	
The action is r	epeated when you press and h	Clear hold the button. Or,	
The action is r you can select	epeated when you press and l a different action below.	Clear hold the button. Or,	
The action is r you can select	epeated when you press and l a different action below.	Clear hold the button. Or,	
The action is r you can select Press and <u>h</u> olo	epeated when you press and i a different action below. : Show or hide Windows i	Clear hold the button. Or, Mobility Center	
The action is r you can select Press and <u>h</u> olo Settings	epeated when you press and la a different action below. : Show or hide Windows i	Clear hold the button. Or, Mobility Center	
The action is r you can select Press and <u>h</u> ok Settings You do not n	epeated when you press and i a different action below. : Show or hide Windows i seed to channe the settings for	Clear hold the button. Or, Mobility Center	
The action is r you can select Press and <u>h</u> ok Settings You do not n	epeated when you press and I a different action below. : <u>Show or hide Windows I</u> eed to change the settings for	Clear hold the button. Or, Mobility Center	
The action is r you can select Press and <u>h</u> ole Settings You do not n	epeated when you press and i a different action below. : Show or hide Windows I sed to change the settings for	hold the button. Or, Mobility Center	
The action is r you can select Press and <u>h</u> ok Settings You do not n	epeated when you press and i a different action below. : Show or hide Windows i ted to change the settings for	Abdity Center	
The action is r you can select Press and <u>h</u> ok Settings You do not n	epeated when you press and I a different action below. : Show or hide Windows I eed to change the settings for	Clear hold the button. Or, Mobility Center	
The action is r you can select Press and <u>h</u> ok Settings You do not n	epeated when you press and 1 a different action below. : Show or hide Windows eed to change the settings for	Clear hold the button. Or, Mobility Center	
The action is r you can select Press and <u>h</u> old Settings You do not n	epeated when you press and i a different action below. : <u>Show or hide Windows</u> eed to change the settings for	I clear hold the button. Or, Mobility Center V r this action.	
The action is r you can select Press and <u>h</u> ok Settings You do not n	epeated when you press and i a different action below. : Show or hide Windows I sed to change the settings for	hold the button. Or, Mobility Center	

11. To reset the camera button to use the camera independent of SIMON, navigate back to this panel and click the "Clear" button shown above with a circle around it.